Gauss's Law:
$$\oint_{S} \vec{E} \cdot d\vec{A} = \frac{q_{\text{enc}}}{\epsilon_{0}}$$

Gauss's Law for B:
$$\oint_{S} \vec{B} \cdot d\vec{A} = 0$$

Faradav's Law:
$$\oint_{L} \vec{E} \cdot d\vec{s} = -\frac{d\Phi_{B}}{dt}$$

Faraday's Law:

$$\oint_{L} \vec{B} \cdot d\vec{s} = \mu_0 I_{enc} + \mu_0 \epsilon_0 \frac{d\Phi_E}{dt}$$

Ampere's Law:

Left side is the field that is being produced.

$$\oint_{S} \vec{E} \cdot d\vec{A} = \frac{q_{\text{enc}}}{\epsilon_{0}}$$


$$\oint_{S} \vec{B} \cdot d\vec{A} = 0$$

$$\oint_{L} \vec{E} \cdot d\vec{s} = -\frac{d\Phi_{B}}{dt}$$


$$\oint_{L} \vec{B} \cdot d\vec{s} = \mu_{0} I_{\text{enc}} + \mu_{0} \epsilon_{0} \frac{d\Phi_{E}}{dt}$$

$$\oint_{S} \vec{E} \cdot d\vec{A} = \frac{q_{\text{enc}}}{\epsilon_{0}}$$
Right side is the source.
$$\oint_{L} \vec{E} \cdot d\vec{s} = -\frac{d\Phi_{B}}{dt}$$

$$\oint_{L} \vec{B} \cdot d\vec{s} = \mu_{0} I_{\text{enc}} + \mu_{0} \epsilon_{0} \frac{d\Phi_{E}}{dt}$$




Charges produce electric field.



There is no charge-like source of magnetic field.

Changing magnetic flux produces electric field.



currents (moving charges) produce magnetic field and changing electric flux produces magnetic field.

Left side is the field that is being produced. Right side $\Phi_{\mathcal{L}} = \frac{\partial \Phi_{\mathcal{E}}}{\partial t} = \frac{\partial \Phi_{\mathcal{E}}}{\partial t}$ Right side is the source.

Gauss's Law:
$$\oint_{S} \vec{E} \cdot d\vec{A} = \frac{q_{\text{enc}}}{\epsilon_{0}}$$

Gauss's Law for B:
$$\oint_{S} \vec{B} \cdot d\vec{A} = 0$$

Faraday's Law:
$$\oint_{L} \vec{E} \cdot d\vec{s} = -\frac{d\Phi_{B}}{dt}$$

$$\oint_{L} \vec{B} \cdot d\vec{s} = \mu_0 I_{\text{enc}} + \mu_0 \epsilon_0 \frac{d\Phi_E}{dt}$$

Ampere's Law:

Today's agenda:

Electromagnetic Waves.

Energy Carried by Electromagnetic Waves.

Momentum and Radiation Pressure of an Electromagnetic Wave.

Maxwell's Equations

Recall:

$$\begin{split} \oint \vec{E} \cdot d\vec{A} &= \frac{q_{enclosed}}{\epsilon_o} \\ \oint \vec{E} \cdot d\vec{s} &= -\frac{d\Phi_B}{dt} \\ \end{split} \qquad \qquad \oint \vec{B} \cdot d\vec{s} = \mu_0 I_{encl} + \mu_0 \epsilon_0 \frac{d\Phi_E}{dt} \end{split}$$

These four equations provide a complete description of electromagnetism.

Maxwell's Equations

$$\oint \vec{E} \cdot d\vec{A} = \frac{q_{enclosed}}{\epsilon_o}$$

$$\oint \vec{E} \cdot d\vec{s} = -\frac{d\Phi_B}{dt}$$

$$\oint \vec{B} \cdot d\vec{A} = 0$$

$$\oint \vec{B} \cdot d\vec{s} = \mu_0 I_{encl} + \mu_0 \varepsilon_0 \frac{d\Phi_E}{dt}$$

 oscillating electric and magnetic fields can "sustain each other" away from source charges and fields

Faraday's law
$$\frac{d}{dt}B \rightarrow E$$
 Ampere's law $\frac{d}{dt}E \rightarrow B$

 result: electromagnetic waves that propagate through space

- electromagnetic waves always involve both \overrightarrow{E} and \overrightarrow{B} fields
- propagation direction, E field and B field form righthanded triple of vectors


Example:

wave propagating in x-direction

E field in y-direction

B field in z-direction

values of E and B depend only upon x and t



Wave equation

- combine Faraday's law and Ampere's law
- for wave traveling in x-direction with \vec{E} in y-direction and \vec{B} in z direction:

Wave equation:

$$\frac{\partial^{2} E_{y}}{\partial x^{2}} = \mu_{0} \varepsilon_{0} \frac{\partial^{2} E_{y}(x,t)}{\partial t^{2}} \qquad \qquad \frac{\partial^{2} B_{z}}{\partial x^{2}} = \mu_{0} \varepsilon_{0} \frac{\partial^{2} B_{z}(x,t)}{\partial t^{2}}$$

• E and B are not independent: $\frac{\partial E_y}{\partial x} = -\frac{\partial B_z}{\partial t}$

Solutions of the wave equation

$$E_{y} = E_{max} sin(kx - \omega t)$$

$$B_z = B_{max} sin(kx - \omega t)$$

E_{max} and B_{max} are the electric and magnetic field amplitudes

Wave number k, wave length λ

$$k = \frac{2\pi}{\lambda}$$

Angular frequency ω , frequency f

$$\omega = 2\pi f$$

Wave speed

$$f\lambda = \frac{\omega}{k} = c$$

$$c = \frac{1}{\sqrt{\mu_0 \varepsilon_0}}$$


$$\frac{\partial \mathsf{E}_{\mathsf{y}}}{\partial \mathsf{x}} = -\frac{\partial \mathsf{B}_{\mathsf{z}}}{\partial \mathsf{t}}$$

$$\frac{\partial \left[\mathsf{E}_{\mathsf{max}} \mathsf{sin} (\mathsf{kx} - \omega \mathsf{t}) \right]}{\partial \mathsf{x}} = -\frac{\partial \left[\mathsf{B}_{\mathsf{max}} \mathsf{sin} (\mathsf{kx} - \omega \mathsf{t}) \right]}{\partial \mathsf{t}}$$

$$E_{max} k cos(kx - \omega t) = B_{max} \omega cos(kx - \omega t)$$

$$\frac{E_{\text{max}}}{B_{\text{max}}} = \frac{E}{B} = \frac{\omega}{k} = c = \frac{1}{\sqrt{\mu_0 \epsilon_0}}.$$


Ratio of electric field magnitude to magnetic field magnitude in an electromagnetic wave equals the speed of light.



This static image doesn't show how the wave propagates.


[Search for "em wave propagation illustration" online to find videos.]

Types of electromagnetic waves



- enormous range of wave lengths and frequencies
- spans more than 15 orders of magnitude

Applications of electromagnetic waves



Today's agenda:

Electromagnetic Waves.

Energy Carried by Electromagnetic Waves.

Momentum and Radiation Pressure of an Electromagnetic Wave.

Energy Carried by Electromagnetic Waves

rate of energy flow:

Poynting vector* \$\rights\$

*J. H. Poynting, 1884.

$$\vec{S} = \frac{1}{\mu_0} \vec{E} \times \vec{B}$$

This is derived from Maxwell's equations.

- \vec{S} represents **energy current density**, i.e., energy per time per area or **power per area** (units $J/(s \cdot m^2) = W/m^2$)
- direction of \overrightarrow{S} is along the direction of wave propagation

$$\vec{S} = \frac{1}{\mu_0} \vec{E} \times \vec{B}$$

$$\vec{S} = \frac{1}{\mu_0} \vec{E} \times \vec{B}$$

for EM wave:
$$|\vec{E} \times \vec{B}| = EB$$

so $S = \frac{EB}{\mu_0}$.

because B = E/c

$$S = \frac{E^2}{\mu_0 C} = \frac{cB^2}{\mu_0}.$$

These equations for S apply at any instant of time and represent the instantaneous rate at which energy is passing through a unit area.

$$S = \frac{EB}{\mu_0} = \frac{E^2}{\mu_0 C} = \frac{CB^2}{\mu_0}$$

EM waves are sinusoidal.
$$E_y = E_{max} sin(kx - \omega t)$$

$$B_z = B_{max} sin(kx - \omega t)$$
 EM wave propagating along x-direction

The average of S over one or more cycles is called the wave intensity I.

The time average of $\sin^2(kx - \omega t)$ is $\frac{1}{2}$, so

$$I = S_{\text{average}} = \left\langle S \right\rangle = \frac{E_{\text{max}}B_{\text{max}}}{2\mu_0} = \frac{E_{\text{max}}^2}{2\mu_0c} = \frac{cB_{\text{max}}^2}{2\mu_0}$$

Notice the 2's in this equation.

This equation is the same as 32-29 in your text, using $c = 1/(\mu_0 \epsilon_0)^{1/2}$.

Energy Density

- so far: energy transported by EM wave
- now: energy stored in the field in some volume of space

energy densities (energy per volume)

$$u_{E} = \frac{1}{2} \varepsilon_{0} E^{2}$$
 $u_{B} = \frac{1}{2} \frac{B^{2}}{\mu_{0}}$

Using B = E/c and c = $1/(\mu_0 \epsilon_0)^{1/2}$:

$$u_{B} = \frac{1}{2} \frac{B^{2}}{\mu_{0}} = \frac{1}{2} \frac{\left(\frac{E}{C}\right)^{2}}{\mu_{0}} = \frac{1}{2} \frac{\mu_{0} \varepsilon_{0} E^{2}}{\mu_{0}} = \frac{1}{2} \varepsilon_{0} E^{2}$$

$$u_{B} = u_{E} = \frac{1}{2} \varepsilon_{0} E^{2} = \frac{1}{2} \frac{B^{2}}{\mu_{0}}$$

remember: E and B are sinusoidal functions of time

total energy density:

$$\mathbf{u} = \mathbf{u}_{\mathrm{B}} + \mathbf{u}_{\mathrm{E}} = \varepsilon_0 \mathbf{E}^2 = \frac{\mathbf{B}^2}{\mu_0}$$
 instantaneous energy densities (E and B vary with time)

 average over one or more cycles of electromagnetic wave gives factor ½ from average of sin²(kx - ωt).

$$\left\langle u_{\text{E}}\right\rangle = \frac{1}{4} \, \epsilon_0 E_{\text{max}}^2 \ , \ \left\langle u_{\text{B}}\right\rangle = \frac{1}{4} \frac{B_{\text{max}}^2}{\mu_0}, \ \text{and} \ \left\langle u\right\rangle = \frac{1}{2} \, \epsilon_0 E_{\text{max}}^2 = \frac{1}{2} \frac{B_{\text{max}}^2}{\mu_0}$$

Recall: intensity of an EM wave

$$S_{\text{average}} = \left\langle S \right\rangle = \frac{1}{2} \frac{E_{\text{max}}^2}{\mu_0 c} = \frac{1}{2} \frac{c B_{\text{max}}^2}{\mu_0} = c \left\langle u \right\rangle$$

Help!

E or **B** individually:

$$u_B(t) = u_E(t) = \frac{1}{2} \varepsilon_0 E^2(t) = \frac{1}{2} \frac{B^2(t)}{\mu_0}$$

$$\langle u_E \rangle = \frac{1}{4} \varepsilon_0 E_{\text{max}}^2$$

$$\langle u_E \rangle = \frac{1}{4} \epsilon_0 E_{\text{max}}^2$$
 $\langle u_B \rangle = \frac{1}{4} \frac{B_{\text{max}}^2}{\mu_0}$,

Total:

$$u(t) = \varepsilon_0 E^2(t) = \frac{B^2(t)}{\mu_0}$$

$$u(t) = \varepsilon_0 E^2(t) = \frac{B^2(t)}{\mu_0}$$
$$\langle u \rangle = \frac{1}{2} \varepsilon_0 E_{max}^2 = \frac{1}{2} \frac{B_{max}^2}{\mu_0}$$

Example: a radio station on the surface of the earth radiates a sinusoidal wave with an average total power of 50 kW.* Assuming the wave is radiated equally in all directions above the ground, find the amplitude of the electric and magnetic fields detected by a satellite 100 km from the antenna.

Strategy: we want E_{max} , B_{max} . We are given average power.

Satellite


From the average power we can calculate intensity, and from intensity we can calculate E_{max} and B_{max} .



*In problems like this you need to ask whether the power is radiated into all space or into just part of space.

Example: a radio station on the surface of the earth radiates a sinusoidal wave with an average total power of 50 kW.* Assuming the wave is radiated equally in all directions above the ground, find the amplitude of the electric and magnetic fields detected by a satellite 100 km from the antenna.

All the radiated power passes through the **hemispherical surface*** so the average power per unit area (the intensity) is




$$I = \left(\frac{power}{area}\right)_{average} = \frac{P}{2\pi R^2} = \frac{\left(5.00 \times 10^4 \text{ W}\right)}{2\pi \left(1.00 \times 10^5 \text{ m}\right)^2} = 7.96 \times 10^{-7} \text{ W/m}^2$$
Today's lecture is brought to you by the letter P.

*In problems like this you need to ask whether the power is radiated into all space or into just part of space.

$$I = \langle S \rangle = \frac{1}{2} \frac{E_{\text{max}}^2}{\mu_0 C}$$

$$\text{E}_{\text{max}} = \sqrt{2\mu_0 c I}$$



$$= \sqrt{2(4\pi \times 10^{-7})(3\times 10^{8})(7.96\times 10^{-7})} \frac{\text{V/m}}{\text{m}}$$
$$= 2.45\times 10^{-2} \frac{\text{V/m}}{\text{m}}$$

$$B_{\text{max}} = \frac{E_{\text{max}}}{c} = \frac{\left(2.45 \times 10^{-2} \text{ V/m}\right)}{\left(3 \times 10^8 \text{ m/s}\right)} = 8.17 \times 10^{-11} \text{ T}$$

You could get Bmax from $I = c B_{max}^2/2\mu_0$, but that's a lot more work

Example: for the radio station in the previous example, calculate the average energy densities associated with the electric and magnetic field at the location of the satelite.

$$\langle \mathbf{u}_{\mathsf{E}} \rangle = \frac{1}{4} \, \varepsilon_0 \mathsf{E}_{\mathsf{max}}^2$$

$$\langle u_{\rm B} \rangle = \frac{1}{4} \frac{B_{\rm max}^2}{\mu_0}$$

$$\left\langle u_{E}\right\rangle =\frac{1}{4}\left(8.85\times10^{-12}\right)\left(2.45\times10^{-2}\right)^{2}\frac{J}{m^{3}} \quad \left\langle u_{B}\right\rangle =\frac{1}{4}\frac{\left(8.17\times10^{-11}\right)^{2}}{\left(4\pi\times10^{-7}\right)}\frac{J}{m^{3}}$$

$$\langle u_{\rm B} \rangle = \frac{1}{4} \frac{\left(8.17 \times 10^{-11} \right)^2}{\left(4\pi \times 10^{-7} \right)} \frac{\rm J}{\rm m^3}$$

$$\langle u_E \rangle = 1.33 \times 10^{-15} \frac{J}{m^3}$$

$$\langle u_{\rm B} \rangle = 1.33 \times 10^{-15} \frac{\rm J}{\rm m^3}$$

If you are smart, you will write $\langle u_B \rangle = \langle u_F \rangle = 1.33 \times 10^{-15} \text{ J/m}^3$ and be done with it.

Today's agenda:

Electromagnetic Waves.

Energy Carried by Electromagnetic Waves.

Momentum and Radiation Pressure of an Electromagnetic Wave.

Momentum of electromagnetic wave

EM waves carry linear momentum as well as energy

momentum stored in wave in some volume of space

momentum density (momentum per volume):

$$\frac{d\langle p \rangle}{dV} = \frac{\langle S \rangle}{c^2} = \frac{I}{c^2}$$
 dp is momentum carried in volume dV

momentum transported by EM wave:

momentum current density (momentum per area and time)

$$c \frac{d\langle p \rangle}{dV} = \frac{\langle S \rangle}{c} = \frac{I}{c}$$

Radiation Pressure

 if EM radiation is incident on an object for a time dt and if radiation is entirely absorbed:

object gains momentum

$$d\langle p \rangle = \frac{\langle S \rangle}{c} A dt$$




- Newton's 2nd Law (F = dp/dt): **force** $\langle F \rangle = \frac{\langle S \rangle}{c} A$
- Radiation exerts pressure

$$\left\langle P_{\text{rad}} \right\rangle = \frac{\left\langle F \right\rangle}{A} = \frac{\left\langle S \right\rangle}{c} = \frac{I}{c}$$

(for total **absorption**)

 if radiation is totally reflected by object, then magnitude of momentum change of the object is twice that for total absorption.

$$d\langle p \rangle = 2 \frac{\langle S \rangle}{c} A dt$$



- Newton's 2nd Law (F = dp/dt): force $\langle F \rangle = 2 \frac{\langle S \rangle}{c} A$
- Radiation exerts **pressure**

$$\left\langle P_{\text{rad}} \right\rangle = \frac{\left\langle F \right\rangle}{A} = 2\frac{\left\langle S \right\rangle}{c} = 2\frac{I}{c}$$

(for total reflection)

$$\langle P_{rad} \rangle = \frac{I}{c}$$
 (total absorption) incident absorbed

Using the arguments above it can also be shown that:

$$\langle P_{rad} \rangle = \frac{2I}{c}$$
 (total reflection) incident reflected

If an electromagnetic wave does not strike a surface, it still carries momentum away from its emitter, and exerts $P_{rad}=I/c$ on the emitter.

Example: a satellite orbiting the earth has solar energy collection panels with a total area of 4.0 m². If the sun's radiation is incident perpendicular to the panels and is completely absorbed, find the average solar power absorbed and the average force associated with the radiation pressure. The intensity (I or S_{average}) of sunlight prior to passing through the earth's atmosphere is 1.4 kW/m².

Power = IA =
$$\left(1.4 \times 10^3 \text{ W/m}^2\right) \left(4.0 \text{ m}^2\right) = 5.6 \times 10^3 \text{ W} = 5.6 \text{ kW}$$

Assuming total absorption of the radiation:

$$P_{\text{rad}} = \frac{S_{\text{average}}}{C} = \frac{I}{C} = \frac{\left(1.4 \times 10^3 \text{ W/m}^2\right)}{\left(3 \times 10^8 \text{ m/s}\right)} = 4.7 \times 10^{-6} \text{ Pa}$$
Caution! The letter P (or p) has been used in this lecture for power, pressure, and

$$F = P_{rad}A = \left(4.7 \times 10^{-6} \, \text{N/m}^2\right) \left(4.0 \, \text{m}^2\right) = 1.9 \times 10^{-5} \, \text{N}$$

power, pressure, and momentum!

Light Mill (Crookes radiometer)

- airtight glass bulb, containing a partial vacuum
- vanes mounted on a spindle (one side black, one silver)
- vanes rotate when exposed to light

This is **NOT** caused by radiation pressure!!

(if vacuum is too good, mill does not turn)

Mill is heat engine: black surface heats up, detailed mechanism leading to motion is complicated, research papers are written about this!



New starting equations from this lecture:

$$\vec{S} = \frac{1}{\mu_0} \vec{E} \times \vec{B}$$

$$u = \frac{1}{2} \left(\epsilon_0 E^2 + \frac{B^2}{\mu_0} \right) = \epsilon_0 E^2 = \frac{B^2}{\mu_0}$$

$$\langle u \rangle = \frac{1}{4} \left(\epsilon_0 E_{\text{max}}^2 + \frac{B_{\text{max}}^2}{\mu_0} \right) = \frac{1}{2} \epsilon_0 E_{\text{max}}^2 = \frac{B_{\text{max}}^2}{2\mu_0}$$

$$\frac{E}{B} = c = \frac{1}{\sqrt{\epsilon_0 \mu_0}}$$

$$I = \langle S \rangle = c \langle u \rangle$$

$$\langle P_{\rm rad} \rangle = \frac{I}{c} \text{ or } \frac{2I}{c}$$

$$k = \frac{2\pi}{\lambda}$$

$$\omega = 2\pi f$$

$$v = f \lambda = \frac{\omega}{k} = \frac{c}{n}$$